

PrecisionID ITF (Interleaved 2 of 5) Barcode Font User Manual

Notice: When you use this product you agree to the End User License Agreement (EULA). The EULA is provided as a file in the package for this product. To view the license online, please visit www.PrecisionID.com/licenses/

Limitations of the demo version: The demo version of this product may be used for evaluation purposes only. In the demo version, a few of the barcodes generated may contain the demo watermark. All other characters and symbols are exactly the same as the purchased version. If you are using the demo version and you would like to order, please visit: <http://www.precisionid.com/>

ITF Symbology Overview.....	1
Product Overview.....	1
Installation.....	2
Microsoft Windows.....	2
Macintosh OS X.....	2
Other operating systems.....	2
Using the fonts to create bar codes	2
Tutorials for Specific Applications.....	2
Microsoft Access.....	2
Microsoft Excel.....	3
Microsoft Word Mail-merge.....	4
Crystal Reports.....	5
Information for Specific Implementations.....	6
Creating Check Digits in other Applications.....	6
Printing Text below the Barcode.....	6
Specifications.....	6
Font point sizes and X dimension (narrow bar width).....	6
Font names and bar code height.....	7
The ITF Character Chart.....	7

ITF Symbology Overview

ITF is also referred to as Interleaved 2 of 5 or I-2/5. ITF barcodes always contain an even number of digits because a single ITF barcode character represents two numbers to achieve the high density. If a number containing an odd number of digits has to be encoded, a leading zero must be added to produce an even number of digits in the Interleaved 2 of 5 bar code.

ITF encodes only numbers in a high density format. A MOD 10 check digit may be included and is optional. All barcodes require start and stop characters.

Product Overview

ITF requires numbers to be interleaved into single characters before printing. Our PrecisionID Font Formatting Components™ are provided with this package to simplify this process and make printing barcodes with our fonts an easy task. The PrecisionID Font Formatting Components™ include a Crystal Reports UFL, Microsoft VBA module for Excel and Access and Visual Basic source code which may also be used as a guide for conversion to other languages. This package also provides working examples for Word, Access, Excel and Crystal Reports.

Installation

Microsoft Windows

Decompress the fonts in the supplied ZIP file with a decompression utility, such as Winzip. Our fonts are compatible with all 32 bit versions of Windows. We recommend using the supplied **Setup.exe** file to install the fonts automatically in Windows. If you wish to manually install the fonts in Windows, open Control Panel and choose Fonts; then choose Install New Font and browse to the folder that contains the fonts with the TTF extension you extracted from the zip file.

Macintosh OS X

Our fonts are compatible with all versions of Macintosh OS Version 10.1 and greater (OS-X). Decompress the fonts in the supplied ZIP file with a decompression utility such as Stuffit Expander. Drag the files with the TTF extension to the Library/Fonts folder of your hard drive. To activate the fonts, restart the application; some applications may require a restart of the computer.

Other operating systems

We supply Windows TrueType (TTF) fonts as well as Binary (PFB) and ASCII (PFA) versions of PostScript fonts. Consult the documentation for your operating system about instructions and which font to install.

Using the fonts to create bar codes

When creating barcodes with our fonts, we recommend using the PrecisionID Font Formatting Components™ which automatically calculate the required Start, Stop and optional MOD 10 check characters and simply return the text that is formatted to the barcode font. When this text is printed with our barcode font, a correct barcode is created.

To calculate the check digit manually, we suggest following the Visual Basic source code we provide. This code is located in the [Examples\VB Module](#) folder of the package.


Tutorials for Specific Applications

The results for the following tutorials are saved in the [examples](#) folder of the product zip file. We encourage you to refer to the examples provided in this folder.

Microsoft Access


To create a barcode in a Microsoft Access report:

1. Run the Setup program to install the fonts and Access Example file.
2. Before we can create barcodes in Access, we must import the required module. Choose Modules – Import and select the Access Example.mdb file, which will be located in the [Program Files\Precision ID ITF Font Package](#) folder.




3. Choose the module to import from the other database; this module should be named [PrecisionID_ITF_Module](#). After it is properly imported, it will appear as one of the modules in the database.

- Open a report in design view and add a text box to your report. The text box will be modified to contain a barcode.
- Right click on the text box and choose properties.
- Place the formula `=PrecisionID_ITF([Table1.Field1])` in the control source property of the text box where *Table1* is the table and *Field1* is the field that contains the data you want to barcode.



- Run the report. You should see that the formula changed the data from the database and appended additional characters at the beginning and ending of the text. You may notice that the numbers from the data are compressed into other characters, this is normal when you are using ITF.
È!-CYo{-Ì
- Size the text box so it is large enough to contain the entire barcode. You will need to adjust both the height and width. Be sure to leave some extra space to the right and left of the barcode on the report. Generally, you need about 3 times the space to the left and right of the barcode as the thickest bar in the ITF barcode.



- Open a report in design view, select the text box and choose one of the PrecisionID fonts such as **PrecisionID ITF T08** and choose 12 for the point size of the font. You must select the appropriate font for the formula you are using. For example, if you have a formula for the ITF barcode, you must select the ITF Font.
- Save and run your report. You should see the barcode appear in the text box.




Microsoft Excel


- NOTE: the **PrecisionID ITF T04** font is formatted specifically for use in Microsoft Excel. Other fonts may work but may not format properly in the cells.
- In this example we will create a barcode in cell B10 using the data from cell A10 for the barcode.

9	Text Data	Barcode
10	0123456789012	
11	0123456789013	

- Extract the **PrecisionID_ITF_Module.bas** file from the package and place it in the “My Documents” folder.
- Before we can create barcodes in Excel, we must import the required module and change the security setting so it will run. In Excel, choose Tools – Macro – Security and set the security level to Medium. Choose Tools – Macro – Visual Basic Editor.



- Choose File – Import File and select the PrecisionID_ITF_Module.bas file from the list of files. After this module is imported, it will be visible in the list of modules. Choose File – Close and return to Excel.




- In cell B8, enter the formula of `=PrecisionID_ITF(A10)` which is required to format the data to the font.

	A	B
9	Text Data	Barcode
10	0123456789012	=PrecisionID_ITF(A10)


- You should notice that the formula changed the data from the spreadsheet and appended additional characters at the beginning and ending of the text. You may notice that numbers from the data are compressed into other characters, this is normal when you are using ITF.

	A	B
9	Text Data	Barcode
10	0123456789012	È!-CYo{I

- With cell B10 selected, choose the **PrecisionID ITF T04** font, which is specifically formatted for use in Microsoft Excel, and choose 12 for the point size. We also recommend centering the text in this cell so the barcode will contain white space before and after the barcode. You must select the appropriate font for the formula you are using. For example, if you have a formula for the ITF barcode, you must use the ITF Font.



- After selecting the bar code font, you should see the barcode appear. Size the width of the column so that there is some white space before and after the bars of the barcode.

	A	B
9	Text Data	Barcode
10	123456789012	

- To create an entire column of barcodes, choose Edit – Copy with cell B10 selected.
- Highlight cells you wish to add barcodes to and choose Edit - Paste. The formula will automatically adjust for the other cells.

Microsoft Word Mail-merge

- Open the mail merge document.
- To create a barcode in a Word mail-merge, we must insert a merge field from a data source that already formatted the text to the barcode font. In this example, we use Excel as the data source. The Excel spreadsheet data source must already be setup with barcodes just like the Excel Tutorial in this document.
- In Word, Choose Tools – Letters and Mailings – Mail Merge and select the Excel spreadsheet for your data source. Be sure to select the columns and range for the cells that contain the data formatted to the barcode font. You may have to go through the Word mail-merge tutorial for assistance if you are unsure of how to connect to a data source or perform a mail-merge.
- When connected to the data source, we insert the merge field of `«FormattedText»` into the document. When we choose the “View Merged Data” option, we see the text formatted to the

barcode font from the data source appear.

Text formatted to barcode font:

È-ÈÇÌ

5. Select the text in the merged data and choose the **PrecisionID ITF 08** font. Make the font 12 points in size.


Barcode Font




Crystal Reports

This example was created in Crystal Reports version 8. Implementation in other versions of Crystal Reports is very similar if not identical. The fonts and UFL are compatible with Crystal version 7 and above.

1. Open your Crystal Report and switch to design mode. In version 8, choose Insert – Formula Field or in version 9 and above choose Report – Formula Workshop.
2. Right Click on Formula Fields and choose New.



3. Give your formula field a name, in this example we will name it **PrecisionID_Barcode1**. In versions 9 and above, if you are asked to use the editor or the expert, choose Use Editor.
4. In the Formula Editor, choose Functions - Additional Functions and select the **PrecisionID_ITF()** function. The U25PrecisionID.dll UFL file must be installed before you can use this formula or you will receive an error. This UFL file is installed by running the Setup.exe file in the font package. The U25PrecisionID.dll file is also provided in the Crystal DLL folder of the Zip file. To manually install it, copy it to the Windows System directory or the directory where the Crystal DLLs are located. When the U25PrecisionID.dll file is installed and active, the PrecisionID formulas will appear in the Formula Workshop under Additional Functions.
5. Place the cursor between the parentheses in the formula and select the field you wish to encode in the barcode from the Report Fields area in the Formula Editor. A correct formula will appear something like **PrecisionID_ITF ({Table1.Field1})** where Table1.Field1 is the table and field of your database.



6. The tables and fields should be visible above in your database connection. Choose Save and Close.
7. From the Field Explorer, drag the **PrecisionID_Barcode1** Formula Field to the report.
8. Choose File – Print Preview. You should see that the formula field formatted the data from the database and appended additional characters at the beginning and ending of the text. You may notice that the numbers from the data are compressed into other characters; this is normal when you are using ITF Auto and the barcode contains 4 or more consecutive number characters.
9. Switch back to design mode, select the formula field and choose the **PrecisionID ITF T08** font. Set the point size to 12 points or to the size appropriate for your application. You must select the appropriate font for the formula you are using and the point size must be large enough for the scanner you are using (we recommend 12 points).
10. Size the formula field so it is large enough to contain the entire barcode. You will need to adjust both the height and width. Be sure to leave some extra space to the right and left of the barcode on the report. Generally, you need about 3 times the space to the left and right of the barcode as the thickest bar in the ITF barcode.



11. The barcode should now be visible when you run your report.



Information for Specific Implementations

Creating Check Digits in other Applications

The easiest method of creating source code for a check digit in a custom application is to use our [PrecisionID_ITF_Module.bas](#) module as a guide. The module was written to be compatible with Visual Basic 6 and Microsoft Office VBA and may be viewed with a text editor. This module is located in the [Examples\VB Module](#) folder of the package.

Printing Text below the Barcode

Human-readable or text fonts are provided in this package. These fonts contain the letter T to designate them as text fonts.

Specifications

Font point sizes and X dimension (narrow bar width)

Our fonts are designed to print with precision on high resolution printers as well as low resolution printers such as 203 dpi thermal barcode printers. When printing at 203 dpi, the point size chosen should be a multiple of 6. When printing at 300 dpi, the point size chosen should be a multiple of 4.

<i>Font point size</i>	<i>X Dimension (narrow bar width) measured in mils (1/1000 of an inch)</i>
6	5
8	7
12 (recommended)	10
16	13
20	16

24	20
36	30

Font names and bar code height

The numbers at the end of the font name is to identify the height of the font in millimeters (mm) when printed at 12 points. Fonts contain the letter “T” just before the 2 digit size are “human readable” fonts that have the text interpretation below.

<i>Font Name</i>	<i>Approximate Font Height at 12 points</i>
PrecisionID ITF 04	.18” or 04mm (use in Excel)
PrecisionID ITF 08	.30” or 08mm
PrecisionID ITF 12	.45” or 12mm
PrecisionID ITF 16	.62” or 16mm
PrecisionID ITF 20	.84” or 20mm
PrecisionID ITF 30	1.2” or 30mm

The ITF Character Chart

The fonts were created according to the chart below. If you have an advanced knowledge of the ITF specifications, you can use this chart to manually create your barcodes and calculate the check digit. The Text column below is based on the ISO Latin 1 Character set*.

<i>Value</i>	<i>ASCII</i>	<i>Text</i>	<i>Value</i>	<i>ASCII</i>	<i>Text</i>
00	0033	!	53	0086	v
01	0034	"	54	0087	w
02	0035	#	55	0088	x
03	0036	\$	56	0089	y
04	0037	%	57	0090	z
05	0038	&	58	0091	[
06	0039	'	59	0092	\
07	0040	(60	0093]
08	0041)	61	0094	^
09	0042	*	62	0095	_
10	0043	+	63	0096	`
11	0044	,	64	0097	a
12	0045	-	65	0098	b
13	0046	.	66	0099	c
14	0047	/	67	0100	d
15	0048	0	68	0101	e
16	0049	1	69	0102	f
17	0050	2	70	0103	g
18	0051	3	71	0104	h
19	0052	4	72	0105	i
20	0053	5	73	0106	j
21	0054	6	74	0107	k
22	0055	7	75	0108	l
23	0056	8	76	0109	m
24	0057	9	77	0110	n
25	0058	:	78	0111	o
26	0059	;	79	0112	p
27	0060	<	80	0113	q

28	0061	=	81	0114	r
29	0062	>	82	0115	s
30	0063	?	83	0116	t
31	0064	@	84	0117	u
32	0065	A	85	0118	v
33	0066	B	86	0119	w
34	0067	C	87	0120	x
35	0068	D	88	0121	y
36	0069	E	89	0122	z
37	0070	F	90	0123	{
38	0071	G	91	0124	
39	0072	H	92	0125	}
40	0073	I	93	0126	~
41	0074	J	94	0197	À
42	0075	K	95	0198	Æ
43	0076	L	96	0199	Ç
44	0077	M	97	0200	È
45	0078	N	98	0201	É
46	0079	O	99	0202	Ê
47	0080	P	START	0203	Ë
48	0081	Q	STOP	0204	Ì
49	0082	R			-
50	0083	S			-
51	0084	T			-
52	0085	U			-

* If problems occur printing extended characters above ASCII 126, configure your operating system to use one of the following character sets: 1252 Latin 1, 1250 Europe, 1251 Cyrillic, 1253 Greek or 1254 Turkish.

© Copyright 2005 PrecisionID.com